

Fig. 1



Fig. 2



Fig. 3



Document contains one or more reports.

Fig. 4



Section at the same level

Fig. 5



Nested section

Fig. 6



Fig. 7

Creating sections

Action	Document Mode	GUI Action	Reaction – Dropping Objects	Reaction – Dropping Values For more information on filters, see Filters & Rank specification	Inter-action with RE
Dragging & dropping dimension or detail objects or values to the section zone with no existing sections but with an existing block (note: users cannot drop measures to this zone)	Structure Mode	When dragging dimension or detail objects or values to the section zone with no existing sections but with an existing block, a line appears to denote where the start of the section will be (note: users cannot drop measures to this zone). Instead of the object icon, a pop up help saying, "Drop here to create a section" should be displayed. 	Inserts dimension or detail objects (one section for each object dropped) as sections, which begins before the block and ends after the block. In the case of dropping multiple objects, the second section will begin immediately after the first section and end immediately before the end of the first section. See adding section when section already exists. 	Inserts dimension or detail objects (one section for each different associated object of values dropped) with filter as sections, which begins before the block and ends after the block. In the case of dropping multiple objects, the second section will begin immediately after the first section and end immediately before the end of the first section. See adding section when section already exists. 	No

Fig. 8

	Values Mode	When dragging dimension or detail objects or values to the section zone with no existing sections but with an existing block, a line appears to denote where the start of the section will be (note: users cannot drop measures to this zone). Instead of the object icon, a pop up help saying, "Drop here to create a section" should be displayed. 	Inserts all dimension or detail object's values (one section for each different object dropped) as sections, which begins before the block and ends after the block. In the case of dropping multiple objects, the second section will begin immediately after the first section and end immediately before the end of the first section. See adding section when section already exists. 	Inserts dimension or detail values (one section for each different associated object of values dropped) as sections, which begins before the block and ends after the block. In the case of dropping multiple objects, the second section will begin immediately after the first section and end immediately before the end of the first section. See adding section when section already exists. 	Yes

Fig. 9

Fig. 10A

Action	Result
1) None.	T1 T2
2) D+D level <Country>	section <Country> COUNTRY T1 T2 .. end section <country>
3) D+D member <USA>	section <country> COUNTRY | T T1 T2 .. end section <country>
4) D+D level <STATE>	section <country> COUNTRY | TT T1 T2 ... section <state> STATE T1 T2 – end section <State> end section <Country>



Fig. 10B



Note: The Help section changes depending on the selection (Number, Percent, Cumulative sum).

Property	Help Text
Number	Keeps top/bottom set number of values
Percent	Keeps values until sum is the percentage of total
Cumulative sum	Keeps values until sum is the set value

Fig. 10C

Tops
35500



Fig. 11

Year	Sales
1999	100
2000	150
2001	140

Fig. 12



Fig. 13